

# GENOA Transformer<sup>®</sup> Compatibility Matrix

Version 3 (Revision 143)

Last Update 06.09.2020



# TABLE OF CONTENTS

1.	GENOA TRANSFORMER ©	3
1.1	Introduction	3
1.2	IBM DOMINO SERVER	4
1.3	IBM Notes Client (on Windows)	4
1.4	IBM TRAVELER SERVER	4
1.5	BlackBerry SERVER	5
1.6	BlackBerry WORK iOS	5
1.7	BlackBerry WORK Android	5

# 1. GENOA TRANSFORMER ©

## 1.1 INTRODUCTION

The compatibility matrix contains the latest information about GENOA Transformer © compatibility with third-party products and services.

Unless otherwise stated, maintenance releases (for example, 1.1.3) have the same system requirements and support levels as their related major release (for example, 1.1).

For information about installing GENOA Transformer ©, see the Installation and upgrade content. GENOA Transformer © supports only the standard character set (non-unicode).

### 1.1.1 LEGEND

Abbreviation	Definition
NS	Not supported. The configuration is not supported.
LS	Limited support. The configuration is supported but the third-party component has not been fully assessed for compatibility.
SUP	Supported. The configuration is supported
PEN	Pending. The configuration is not yet supported, but the third-party component is currently being assessed for compatibility

## 1.2 IBM DOMINO SERVER

Domino Server	V3.3	V3.2	V3.1	V3.0
9.0.1.9	SUP	SUP	SUP	SUP
9.0.1.10	SUP	SUP	SUP	SUP
10.0.0.0	SUP	SUP	SUP	NS
10.0.1.0	SUP	SUP	SUP	NS
10.0.1.1	SUP	SUP	SUP	NS
10.0.1.2	SUP	SUP	SUP	NS
10.0.1.3	SUP	NS	NS	NS
10.0.1.4	SUP	NS	NS	NS
11.0.0.0	SUP*	NS	NS	NS
11.0.1.0	SUP*	NS	NS	NS

## 1.3 IBM NOTES CLIENT (ON WINDOWS)

Notes Client	V3.3	V3.2	V3.1	V3.0
9.0.1.8	SUP	SUP	SUP	SUP
9.0.1.9	SUP	SUP	SUP	SUP
9.0.1.10	SUP	SUP	SUP	SUP
10.0.0.0	SUP	SUP	SUP	NS
10.0.1.0	SUP	SUP	SUP	NS
10.0.1.1	SUP	SUP	SUP	NS
10.0.1.2	SUP	SUP	SUP	NS
10.0.1.3	SUP	SUP	NS	NS
10.0.1.4	SUP	NS	NS	NS
11.0.0.0	SUP	NS	NS	NS
11.0.1.0	SUP	NS	NS	NS

## 1.4 IBM TRAVELER SERVER

Traveler Server	V3.3	V3.2	V3.1	V3.0
9.0.1.18	NS	NS	LS	LS
9.0.1.19	NS	NS	LS	LS
9.0.1.20	LS	LS	LS	LS
9.0.1.21	LS	LS	SUP	SUP
10.0.0.0	SUP	SUP	SUP	NS
10.0.1.0	SUP	SUP	SUP	NS
10.0.1.1	SUP	SUP	SUP	NS
10.0.1.2	SUP	SUP	SUP	NS
11.0.0.0	SUP*	NS	NS	NS
11.0.1.0	SUP*	NS	NS	NS

\*minimum requirement: V3.3.0.4

## 1.5 BLACKBERRY SERVER

Server	V3.3	V3.2	V3.1	V3.0
BUEM 12.8	NS	LS	LS	SUP
BUEM 12.9	NS	SUP	SUP	SUP
BUEM 12.10	NS	SUP	SUP	SUP
BUEM 12.11	SUP	SUP	SUP	LS
BUEM 12.12	SUP	SUP	SUP	LS
BUEM 12.13	SUP*	LS	LS	LS
BEMS 2.8.x	NS	LS	LS	SUP
BEMS 2.9.x	LS	SUP	SUP	SUP
BEMS 2.10.x	SUP	SUP	SUP	SUP
BEMS 2.12.x	SUP	SUP	SUP	SUP
BEMS 2.13.x	SUP	SUP	SUP	SUP
BEMS 3.1.x	SUP*	LS	LS	LS

## 1.6 BLACKBERRY WORK IOS

BlackBerry WORK	V3.3	V3.2	V3.1	V3.0
2.20.0	SUP	SUP	SUP	SUP
2.20.1	SUP	SUP	SUP	SUP
2.20.2	SUP	SUP	SUP	SUP
3.0.0	SUP	SUP	SUP	SUP
3.1.0	SUP	SUP	SUP	SUP
3.2.0	SUP*	LS	LS	LS

## 1.7 BLACKBERRY WORK ANDROID

BlackBerry WORK	V3.3	V3.2	V3.1	V3.0
2.20.0.1363	SUP	SUP	SUP	SUP
2.20.1.1301	SUP	SUP	SUP	SUP
3.0.0.1409	SUP	SUP	SUP	SUP
3.1.0.1467	SUP	SUP	SUP	SUP
3.2.0.1512	SUP*	LS	LS	LS